

DI-524 - Windows Internet Explorer

http://192.168.0.200/h_jan.html

File Edit View Favorites Tools Help

Google

DI-524

D-Link
Building Networks for People

Air Plus G™
802.11g/2.4GHz Wireless Router

DI-524

Wizard

Wireless

WAN

LAN

DHCP

Home Advanced Tools Status Help




LAN Settings

The IP address of the DI-524.

IP Address

Subnet Mask

Local Domain Name (optional)

Apply Cancel Help

Internet 100%

DI-524 - Windows Internet Explorer

http://192.168.0.200/h_dhcp.html

File Edit View Favorites Tools Help

Google

DI-524

D-Link
Building Networks for People

Air Plus G™
802.11g/2.4GHz Wireless Router

DI-524

Wizard

Wireless

WAN

LAN

DHCP

Home Advanced Tools Status Help

DHCP Server
The DI-524 can be setup as a DHCP Server to distribute IP addresses to the LAN network.

DHCP Server Enabled Disabled

Starting IP Address 192 . 168 . 0 .

Ending IP Address 192 . 168 . 0 .

Lease Time

Static DHCP
Static DHCP is used to allow DHCP server to assign same IP address to specific MAC address.

Enabled Disabled

Name

IP 192 . 168 . 0 .

MAC Address - - - - -

DHCP Client

Done Internet 100%

DI-524 - Windows Internet Explorer

http://192.168.0.200/adv_virtual.html

File Edit View Favorites Tools Help

Google

Go Bookmarks PageRank 3777 blocked Check Settings

DI-524 Home Feeds (1) Print

Home Advanced Tools Status Help

Virtual Server

Virtual Server is used to allow Internet users access to LAN services.

Enabled Disabled

Name

Private IP

Protocol Type

Private Port

Public Port

Schedule Always

From time : AM to : AM

day to

Virtual Servers List

Name	Private IP	Protocol	Schedule	
<input type="checkbox"/> Virtual Server FTP	0.0.0.0	TCP 21/21	always	
<input type="checkbox"/> Virtual Server HTTP	0.0.0.0	TCP 80/80	always	
<input type="checkbox"/> Virtual Server HTTPS	0.0.0.0	TCP 443/443	always	
<input type="checkbox"/> Virtual Server DNS	0.0.0.0	UDP 53/53	always	
<input type="checkbox"/> Virtual Server SMTP	0.0.0.0	TCP 25/25	always	
<input type="checkbox"/> Virtual Server POP3	0.0.0.0	TCP 110/110	always	
<input type="checkbox"/> Virtual Server Telnet	0.0.0.0	TCP 23/23	always	
<input type="checkbox"/> IPSec	0.0.0.0	UDP 500/500	always	
<input type="checkbox"/> PPTP	0.0.0.0	TCP 1723/1723	always	
<input type="checkbox"/> NetMeeting	0.0.0.0	TCP 1720/1720	always	
<input checked="" type="checkbox"/> Sputnik-7050	192.168.0.104	TCP 7050/7050	always	
<input checked="" type="checkbox"/> Sputnik-7060	192.168.0.104	TCP 7060/7060	always	
<input checked="" type="checkbox"/> Sputnik-7070	192.168.0.104	TCP 7070/7070	always	
<input checked="" type="checkbox"/> Sputnik-7080	192.168.0.104	TCP 7080/7080	always	
<input checked="" type="checkbox"/> Sputnik-7090	192.168.0.104	TCP 7090/7090	always	
<input checked="" type="checkbox"/> Sputnik-7040	192.168.0.104	TCP 7040/7040	always	
<input checked="" type="checkbox"/> Voltek-1	192.168.0.100	Both 80/80	always	
<input checked="" type="checkbox"/> Voltek-2	192.168.0.100	UDP 5002/5002	always	
<input checked="" type="checkbox"/> Voltek-3	192.168.0.100	UDP 5003/5003	always	

Done Internet 100%

DI-524 - Windows Internet Explorer

http://192.168.0.200/adv_firewall.html

File Edit View Favorites Tools Help

Google

DI-524

D-Link
Building Networks for People

Air Plus G™
802.11g/2.4GHz Wireless Router

DI-524

Virtual Server

Applications

Filters

Firewall

DMZ

Performance

ZoneAlarm

Home **Advanced** Tools Status Help

Firewall Rules

Firewall Rules can be used to allow or deny traffic from passing through the DI-524.

Enabled Disabled

Name

Action Allow Deny

Interface IP Range Start IP Range End Protocol Port Range

Source *

Destination * TCP -

Schedule Always

From time 00 : 00 AM to 00 : 00 AM

day Sun to Sun

Firewall Rules List

Action	Name	Source	Destination	Protocol
<input checked="" type="checkbox"/>	Allow Sputnik-7050	WAN,*	LAN,192.168.0.104	TCP,7050
<input checked="" type="checkbox"/>	Allow Sputnik-7060	WAN,*	LAN,192.168.0.104	TCP,7060
<input checked="" type="checkbox"/>	Allow Sputnik-7070	WAN,*	LAN,192.168.0.104	TCP,7070
<input checked="" type="checkbox"/>	Allow Sputnik-7080	WAN,*	LAN,192.168.0.104	TCP,7080
<input checked="" type="checkbox"/>	Allow Sputnik-7090	WAN,*	LAN,192.168.0.104	TCP,7090
<input checked="" type="checkbox"/>	Allow Sputnik-7040	WAN,*	LAN,192.168.0.104	TCP,7040
<input checked="" type="checkbox"/>	Allow Voltek-2	WAN,*	LAN,192.168.0.100	UDP,5002
<input checked="" type="checkbox"/>	Allow Voltek-3	WAN,*	LAN,192.168.0.100	UDP,5003
<input checked="" type="checkbox"/>	Allow Allow to Ping WAN port	WAN,*	LAN,192.168.0.200	ICMP,8
<input checked="" type="checkbox"/>	Allow Voltek-1	WAN,*	LAN,192.168.0.100	*,80
<input checked="" type="checkbox"/>	Deny Default	*,*	LAN,*	*,*
<input checked="" type="checkbox"/>	Allow Default	LAN,*	*,*	*,*

Internet 100%

DI-524 - Windows Internet Explorer

http://192.168.0.200/tools_admin.html

File Edit View Favorites Tools Help

Google

Go

Bookmarks PageRank 3777 blocked Check

DI-524

Home Feeds (1) Print

D-Link
Building Networks for People

Air Plus G™
802.11g/2.4GHz Wireless Router

DI-524

Admin

Time

System

Firmware

Misc.

Home Advanced **Tools** Status Help

Administrator Settings
Administrators can change their login password.

Administrator (The Login Name is "admin")

New Password

Confirm Password

User (The Login name is "user")

New Password




Confirm Password

Remote Management

Enabled Disabled

IP Address *

Port 8080

  
Apply Cancel Help

Done

Internet

100%